




Operating Systems and Languages Library

MS-DOS

Quick Reference Guide



olivetti



**How to position your
Quick Reference Guide**

PREFACE

This booklet is a Quick Reference Guide for the MS-DOS operating system. It describes Microsoft Version 3.30 of MS-DOS, and is for anyone who wishes to use this operating system on an Olivetti Personal Computer.

*Copyright © Microsoft Corporation
1981 ÷ 1987*

*Copyright © 1989 by Olivetti
All rights reserved*

PUBLICATION ISSUED BY:

Ing. C. Olivetti & C., S.p.A.
Direzione Documentazione
77, Via Jervis - 10015 Ivrea (Italy)

MS-DOS Parameters - MS-DOS Switches

MS-DOS Parameters

<i>d:</i>	Disk drive letter.
<i>drive:</i>	Disk drive letter.
<i>date</i>	USA (default): Date in format month-day-year (mm-dd-yy). EUROPE: Date in format day-month-year (dd-mm-yy).
<i>.ext</i>	Up to three-character extension to the filename.
<i>filename</i>	Up to eight-character name of the file on disk.
<i>filespec</i>	Disk drive letter and filename.
<i>path</i>	Disk drive letter and directory location.
<i>pathname</i>	Path to and name of the file.

time Time in format [hours:minutes [:seconds [.hundreths]]
Note The delimiter setting (:) is country dependent.

stdin Standard input
stdout Standard output, default is CON but may be replaced by a device or file.

Control Keys

Press **CTRL C** or **CTRL BREAK** to abort commands.

Press **CTRL P** or **CTRL PRTSC** to echo screen to printer.

Press **SHIFT PRTSC** to print the screen.

Press **CTRL S** or **CTRL NUMLOCK** or **PAUSE** to stop screen scrolling: press any key to resume.

Syntax Rules

Separate commands and parameters by delimiters, i.e. a space (), a comma (,), a semicolon (;), or an equal sign (=).

Enter all words printed in bold capitals e.g. **COPY**, **BACKUP**, **DATE**, but you may use either small or capital letters.

Supply values for words shown in lowercase italic letters, e.g. *pathname*.

Enter all punctuation exactly as shown, except for square brackets, vertical bars, and braces.

[] You may choose an option in square brackets.

{ | } You must choose an option separated by a vertical bar in braces.

... Repeat an item followed by an ellipsis as often as you wish.

Reserved File Names

Do not use the following names either as filenames or as extensions:
AUX, COM1, COM2, CON, LPT1, LPT2, LPT3, NUL, or PRN.

MS-DOS Switches

The switch is followed here by the MS-DOS command where you may use it. Note that a switch can have a different function with different commands.

/# FC Number of lines in a file that must match to resynchronize after a mismatch (default = 2).

/+ *number*
SORT Sort data by characters starting with this column number.

MS-DOS Switches

/1 DISKCOMP Compare only the first side of the diskette.

DISKCOPY Copy only the first side of the diskette.

FORMAT Format single-sided diskette.

/4 FORMAT Format 48 tpi diskette in 96 tpi drive.

/8 DISKCOMP Compare only eight sectors per track on the diskette.

FORMAT Format each diskette with only eight sectors per track.

+A ATTRIB Sets the archive attribute of a file.

-A ATTRIB Clears the archive attribute of a file.

/A BACKUP Add the files to the diskette presently in the drive.

COPY With a source file: regard this as an ASCII text file and copy it up to the first end-of-file character (**CTRL Z**).

COPY With a target file: regard this as an ASCII text file and add an end-of-file character (**CTRL Z**) as the last character.

REPLACE Add new files to the target directory instead of replacing existing ones.

XCOPY Copy files that have their archive bit set. The archive bit of the source file is not modified.

/A: date

RESTORE Only those files that were last modified on or after the given date should be restored.

/a

FC Displays only the lines that begin each set of differences. The intermediate lines are represented by ellipsis (...).

/B COPY With a source file: regard this as a binary file and copy it including any end-of-file characters.

COPY With a target file: regard this as a binary file and do not add an end-of-file character.

FORMAT Leave room on diskette for MS-DOS hidden system files.

GRAPHICS The background color is printed, otherwise the background is suppressed.

/B: date

RESTORE Only those files which were modified on or before the given date should be restored.

/b

FC Perform a binary comparison of the files and do not resynchronize after a mismatch.

/C *command-string*

COMMAND Obey the following *command-string*.

/C FIND Print how many lines contain the string.

PRINT Turn on print cancel mode: suspend these files from the print queue.

/c FC Consider all letters as uppercase.

/D GRAPHICS For a machine with an EGC, but no resident DEB INT 10 installed.

JOIN To unsplice a join.

REPLACE Replace files in the target directory only if the source files are newer than the corresponding target files.

SUBST To delete a substitution.

MS-DOS Switches

- /D: date**
BACKUP Copy only those files created or edited since this date.

XCOPY Copy source files that have been created or modified on or after this date.
- /E** APPEND MS-DOS keeps the APPEND paths in the environment.

XCOPY Copy empty sub-directories. Use with /S switch.
- /E: nnnnn**
COMMAND Specifies the environment size, *nnnnn* can range between 160 and 32768 bytes.
- /E: time**
RESTORE Copy only those files which were modified at or earlier than the given time.
- /F** BACKUP Formats, unformatted disks before backing up. Uses FORMAT.

CHKDSK Correct any errors found.

TREE Lists the files in each directory.
- /F: memory-space**
SHARE The amount of memory space reserved for recording file sharing information. The default memory space for file sharing information is 2048 bytes.
- /H** GRAPHICS 200 scanlines (Industry Standard Compatible).
- /L: pathname**
BACKUP Makes a backup log entry in the specified file.
- /L: locks**
SHARE Allocates maximum number of locks it is possible to apply to a file. The default value is 20 locks.
- /L: time**
RESTORE Only those files that were last modified at or later than the given time should be restored.
- /I** FC Compares the files in ASCII mode. It is the default when you compare files that do not have extensions of .EXE, .COM, .SYS, .OBJ, .LIB, or .BIN.
- /Ib length**
FC Sets the Internal Line Buffer to length of lines. The default length of the internal buffer is 100 lines.
- /M** BACKUP Only copy files changed since last backup.

RESTORE Restore only those files modified since last backup.

XCOPY Only copy files with their archive bit set. Turns off the archive bit.
- /N** FIND Display the relative line number of each line in the file.

RESTORE Only those files that no longer exist on the restore-drive should be restored.
- /N: sectors**
FORMAT the diskette to have the given number of sectors.
- /n** FC The line numbers are displayed on ASCII comparisons.
- /P** COMMAND Makes copy of COMMAND.COM permanent.

DIR Stop displaying the directory when the screen is full. Press any key to continue.

PRINT Turn on print mode: add these files to print queue.

REPLACE Prompts you before replacing or adding a file.

MS-DOS Switches - MS-DOS Commands

- RESTORE Prompts you before restoring files modified since last backup.
- XCOPY Prompts you before copying each file.
- +R ATTRIB Sets the read-only attribute of a file.
- R ATTRIB Clears the read-only attribute of a file.
- /R GRAPHICS Black is printed black and white is printed white, otherwise printing is reversed.
- REPLACE Replace read-only files as well as unprotected files.
- SORT Sort data in reverse ASCII order.
- /S ATTRIB File(s) in the specified directory and subdirectories will be processed.
- BACKUP Copy all files in directory and all its subdirectories.
- FORMAT Copy the system files to the disk.
- REPLACE Search all subdirectories of the target directory, while replacing matching files.
- RESTORE Restore files in all subdirectories.
- XCOPY Recursively copy lower level subdirectories and their files.
- /T PRINT Terminate all files in the print queue.
- /T: *time* BACKUP Backs up only those files that you last modified at or after the given time.
- /T: *tracks* FORMAT a diskette to have the given number of tracks.
- /t FC Tabs are not expanded to spaces.
- /U GRAPHICS 400 scanlines (Olivetti High Resolution).
- /V CHKDSK Display status messages.
- COPY Verify the copied file.
- FIND Display all lines not containing the string.
- FORMAT Enter a volume label on this diskette.
- XCOPY Verify the copied file.
- /W DIR Display only the file names widthwise.
- REPLACE Wait before replacing or adding files.
- XCOPY Wait before starting to copy files.
- /w FC Compress tabs and spaces during the file comparison.
- /X APPEND Commands such as COMP, DIR and COMMAND /C will search for files as if they were in the current directory.

MS-DOS Commands

[drive:][path] APPEND [/X][/E]

or

[drive:][path] APPEND [=][drive:] path
[;[drive:]path...]

The first time APPEND is called: sets a search path for data files.

APPEND [=][drive:] path
[;[drive:]path...]

or

APPEND

or

APPEND [=];

Subsequent calls to modify the append path or to show the path or to delete the path.

MS-DOS Commands

[d:][path] ASSIGN [drive1 = drive2]...

Routes all requests for the first drive to the second drive. Enter without parameters to reset.

[d:][path] ATTRIB [+R|-R] [+A|-A] pathname/S

Sets or resets the read only attribute and/or archive bit attribute of a file. With only *pathname* as a parameter, displays the attribute setting.

[d:][path] BACKUP source-drive: [pathname]target-drive: [/S] [/M] [/A] [/F] [/D:date] [/T:time] [/L[pathname]]

Creates a back-up of one or more disk files from a hard disk or high capacity diskette on a series of diskettes or a hard disk.

BREAK [ON|OFF]

Turns **CTRL C** or **CTRL BREAK** the abort key on or off.

CALL [drive:][path] batchfile

Calls a batch file from within a batch file and returns to the calling batch file.

CHCP [nnn]

Displays or changes the system code page.

CD or CHDIR [drive:][path]

With a *path* changes the current directory. Without a *path* displays the name of the current working directory.

[d:][path] CHKDSK [drive:][path] [filename] [/F] [/V]

Check disk and reports file and memory status.

CLS

All data on the display screen is cleared and the cursor is moved to the home position.

[d:][path] COMMAND [drive:shellpath][cttydev] [/E: nnnnn] [/P] [/C command-string]

Starts a new command processor.

[d:][path] COMP [pathname1 [pathname2]]

Compare the first file with the second file.

COPY [/A|/B] pathname1 [/A|/B][+ pathname2 [/A|/B]...] [pathname [/A|/B]][/V]

Copies one or more files. Alternatively files maybe concatenated and copied to a destination file.

CTTY device

Changes the input/output console from which you issue commands.

DATE [date]

Displays or sets the system date.

DEL or ERASE pathname

Deletes the specified file(s) from disk.

DIR [pathname] [/P] [/W]

Lists details of the files in the current or specified directory.

[d:][path] DISKCOMP [drive1: [drive2:]] [/1] [/8]

Compare contents of first diskette with second diskette.

[d:][path] DISKCOPY [sourcedrive:] [targetdrive:]/[1]

Copies the contents of a diskette onto another diskette.

[@] ECHO [ON|OFF] message

Turns the batch file echo feature on/off or display message.

[d:][path] EXE2BIN pathname1 [pathname2]

Converts files from EXEcutable format to BINary format.

EXIT

Exits from a secondary command processor and returns to a parent program or command processor.

MS-DOS Commands

[d:][path] FASTOPEN *drive:* [nnn]...

Decreases the amount of time needed to open frequently-used files and directories. The default and minimum value for *nnn* is 10 files or directories.

[d:][path] FC [/#] [/a][/b][/c][/l][/n] [/t][/w][/lb *length*] *filename1 filename2*

Compares the contents of two files.

[d:][path] FDISK

Sets up the MS-DOS partition(s) for the hard disk(s).

[d:][path] FIND [/V][/C][/N] "*string*" [*pathname*]...

Searches for a specific string of text in a file or files.

FOR %*char* IN (*item ...*) **DO**

[*command*] %*char* (Interactive entry)

FOR %%*char* IN (*item ...*) **DO**

[*command*] %%*char* (Batch entry)

Allows iterative execution of MS-DOS commands.

[d:][path] FORMAT *drive:* [/1] [/1] [/8] [/B] [/S] [/V] [/N:*sectors*] [/T:*tracks*]

Formats a disk to receive MS-DOS files.

GOTO *label*

Jumps to a label in a batch file (in the file precede label with a colon, e.g. :LABEL).

[d:][path] GRAFTABL [nnn][/STATUS]

Loads a table of extended ASCII characters, to enable them to be displayed when using a display in graphics mode.

[d:][path] GRAPHICS [*printer-type*] [/B][/R][/D] [/U][/H]

Enables graphics currently displayed on the screen to be printed along with any text when the **SHIFT PRtSc** keys are pressed.

[d:][path] GWBASIC

Enters the MS GW-BASIC interpreter.

[d:][path] HEXDUMP [*drive:*] *filename*

Displays the contents of a file, byte by byte, in hexadecimal.

IF [NOT] *condition command*

Causes conditional execution of a command in a batch file.

[d:][path] JOIN *connected-drive splice-drive:\splice-directory*

Joins a disk drive to an empty directory on another drive to produce a single directory structure.

[d:][path] JOIN *connected-drive: /D*

With a parameter unsplices a join. Without a parameter shows the status of the join.

[d:][path] KEYB [*xx[,yyy]*, [*pathname*]]

Loads a Keyboard definition program. KEYB without parameters displays the current status.

[d:][path] LABEL [*drive:*][*volume-label*]

Creates, changes or deletes a disk volume label.

MD (or **MKDIR**) *path*

Make a new directory.

[d:][path] MODE COM*n*:*baud*[, *parity* [, *databits*[, *stopbits*[,**P**]]]

Sets the protocol for an RS-232C port.

[d:][path] MODE *n* or **MODE** [*n*] , *m* [,**T**]

Set monitor mode (T = display test pattern).

[d:][path] MODE LPT# : [*chars*] [, *spacing*] [**P**]

Sets the mode of operation for a compatible printer.

[d:][path] MODE LPT# : = COM*n*

Redirects the output for any printer to a communications port.

MS-DOS Commands

[d:][path] MODE device CODEPAGE PREP[ARE] = ((nnn[,nnn...]) pathname
[d:][path] MODE device CODEPAGE SEL[ECT] = nnn
[d:][path] MODE device CODEPAGE REF[RESH]
[d:][path] MODE device CODEPAGE [/STATUS]

Sets or displays code pages for parallel printers or your console screen device.

[d:][path] MORE

Sends output to the terminal one screen at a time.

[d:][path] NLSFUNC [pathname]

Loads country-specific information.

PAUSE [comment]

Suspends execution of the batch file in which it is contained.

[d:][path] PRINT [/D: device] [/B: bufsize] [/U: busysticks] [/M: maxticks] [/S: timeslice] [/Q: queuesize] [[pathname]...]

(The first time PRINT is called.) Queues text files for background printing.

[d:][path] PRINT [[pathname] [/C|/P|/T]...]

Subsequent calls can add (/P), or cancel (/C) files from the queue or empty (/T) files from the queue. PRINT on its own displays the list of files in the queue.

PROMPT [[meta-character|character]...]

Sets the MS-DOS command prompt.

[d:][path] RECOVER [drive:][pathname]

Recovers a file or an entire disk containing faulty sectors.

REM [remark]

Displays a remark during the execution of a batch file.

REN (or RENAME) pathname filename

Renames files.

[d:][path] REPLACE [source-drive:] [source-path]source-file [target-drive] [target-path] [/A]/P[/R]/S[/W]

Updates or adds files according to the criteria set by the option switches.

[d:][path] RESTORE source-drive: [target-drive:][pathname] [/S]/P[/B: date]/A:date[/E: time]/L:time[/M]/N

Restores files from disk(ette) to disk, (the disks must have been created using the BACKUP command).

RD (or RMDIR) [drive:] path

Removes a directory.

[d:][path] SELECT [[s-drive] t-drive:[t-path]] country-code keyboard-code

Copies your MS-DOS system diskette to create a working copy for your selected country and keyboard.

WARNING: This command formats the target drive. Only use for installing MS-DOS for the first time onto unused disks.

SET [key = value]

Assigns one string value in the environment to another key string; for use in application programs or batch files.

[d:][path] SHARE [/F: memory space] [/L: locks]

Installs Network file and record locking. Installs a resident facility, which checks for diskette removal during reading and writing to diskettes.

SHIFT

Allows access to more than 9 replaceable parameters in batch processing.

[d:][path] SORT [pathname] [/R] [/ + number]

Sorts data in forward or reverse ASCII order.

[d:][path] SUBST dummy-drive: pathname

Substitute a dummy drive specifier for a pathname.

MS-DOS Commands - DEBUG The Debugger

[d:][path] SUBST [dummy-drive: /D]

To delete the dummy drive substitution. SUBST with no parameters displays the current substitution.

[d:][path] SYS drive:

Updates the specified disk with the hidden system files. The source disk must be the default drive.

TIME [time]

Displays or sets the system time.

[d:][path] TREE [drive:] [/F]

Displays all the directories and paths on the specified drive. It also has an option to list the files in each directory.

TYPE pathname

Displays the contents of the specified file on the screen.

VER

Displays the version number of MS-DOS you are using.

VERIFY [ON|OFF]

Verify data written to disk, (same function as COPY /V switch).

VOL [drive:]

Displays the volume label of the disk in the specified or default drive.

[d:][path] XCOPY [source-drive:] [source-path] source-filename [target-drive:][target-path][target-filename] [/A][/D:mm-dd-yy][/E][/M][/P][/S][/V] [/W]

Copies files and directories, including lower level directories if they exist.

DEBUG The Debugger

[d:][path] DEBUG [[path]filespec [, arglist]]

DEBUG Parameters

address Hexadecimal value in one of these formats:

segment register, colon, hexadecimal offset, e.g. DS:0300
hexadecimal segment, colon, hexadecimal offset, e.g. 9D0:0100
hexadecimal offset value, e.g. 200

byte One- or two-character hexadecimal value.

bytevalue Hexadecimal byte value.

drive The drive you wish to select (0 = drive A; 1 = drive B; 2 = drive C).

range Range of addresses, specified as either: *address* **L** *value* (*address* = start of range, *value* = length of range), or *address* , *address* (*addresses* = start and end of range).

value One- to four-character hexadecimal value.

DEBUG Commands

ASSEMBLE

A [address]

Assemble 8086 mnemonics directly in memory.

COMPARE

C range , address

Compare two areas of memory.

DUMP

D [range | address]

Display this area of memory.

ENTER

E address [, bytevalue [, bytevalue]...]

Replace value at *address* with *bytevalue*.

FILL

F range , bytevalue [, bytevalue ...]

Fill *range* with *bytevalue*.

DEBUG The Debugger - LINK The Linker

GO

G [= *address*][, *address*]...

Execute program from = *address* with breakpoints at *address* to display registers.

HEX

H *value-a* , *value-b*

Display sum and difference of two hexadecimal values.

INPUT

I *value*

Input and display byte from port (*value* = *port address*).

LOAD

L [*address* [, *drive* , *sector-a* , *sector-b*]]

Load file or absolute disk sectors into memory.

MOVE

M *range* , *address*

Move range of memory to new location starting at address.

NAME

N [*path*]*filespec* [, *arglist*]

Name file and provide parameters.

OUTPUT

O *value* , *byte*

Send this byte to an output port.

PROCEED

P [= *address*][, *value*]

Proceed through CALL and INT instructions.

QUIT

Q

Quit DEBUG and discard file.

REGISTER

R [*register-name* | **F**]

Display or change register and flags.

SEARCH

S *range* , *list*

Search range for list of bytes.

TRACE

T [= *address*][, *value*]

Execute instructions, display register contents, flag settings, and next instruction.

UNASSEMBLE

U [*range* | *address*]

Unassemble instructions.

WRITE

W [*address* [, *drive* , *sector-a* , *sectors*]]

Write file or absolute disk sectors to disk.

LINK The Linker

LINK Switches

/D or /DSALLOCATE

Load all data defined to be in DGROUP at high end of group. (Default = load all data at low end of group.)

/H or /HIGH

Load the run file as high as possible in memory. (Default = load run file as low as possible.)

DO NOT USE THIS SWITCH WITH PASCAL OR FORTRAN PROGRAMS.

/L or /LINENUMBERS

Include the line numbers and addresses of the source statements from the input modules, in the list file.

/M or /MAP

List, in alphabetical order, all public (global) symbols defined in the output modules. (Default = list only errors and undefined global symbols.)

/N or /NODEFAULTLIBRARY

SEARCH

Do not automatically search the default library to resolve external references.

LINK The Linker - EDIT The Video File Editor

/P or /PAUSE

Pause to change disks before MS-LINK outputs the run (.EXE) file.

DO NOT CHANGE A DISKETTE THAT IS TO RECEIVE A LIST FILE, OR THAT IS USED FOR A TEMPORARY (VM.TMP) FILE.

/S: or /STACK: size

Override the stack size provided by the macro assembler or compiler for the load module. (Entering 1 to 511 defaults to 512.)

LINK Parameters

libfile Pathname of a library file (default ext = .LIB)

listfile Pathname of the list file (default = NUL.MAP)

objfile Pathname of an object module you wish to link (default ext = .OBJ)

runfile Pathname of a run (executable) file you wish to create (ext = .EXE)

Interactive Entry

[d:][path] LINK

Object Modules [OBJ]:
objfile[+ objfile]... [switch]...

Run File [objfile.EXE]:
[runfile][switch]...

List File [NUL.MAP]:
[listfile][switch]...

Libraries [.LIB]:
[libfile[+ libfile]...][switch]...

Command Line Entry

[d:][path] LINK objfile[+ objfile]...
[switch]... [, [runfile][switch]... [, [listfile]
[switch]... [, [libfile[+ libfile]...][switch]...]]

Automatic Response File Entry

[d:][path] LINK @pathname

EDIT The Video File Editor

[d:][path] EDIT [/B][/T][/R] pathname

/B Create a back up file

/T Replace spaces with TABS

/R Read-only

EDIT Function Keys

SHIFT F1
F1 Discard and quit
Command mode

SHIFT F2
F2 Delete a line
Restore lines from buffer

SHIFT F3
F3 Split line
Join lines

SHIFT F4
F4 Go to start of line
Go to end of line

SHIFT F5
F5 Save and exit
Save and continue

SHIFT F6
F6 Erase to end of line
Move cursor to next line

SHIFT F7
F7 Insert MARK line in text
Move cursor to MARK
line

SHIFT F8
F8 Search to start of file
Search to end of file

SHIFT F9
F9 Move up a line
Move down a line

SHIFT F10
F10 Move up a half screen
Move down a half screen

ESC To enter control characters

EDIT The Video File Editor - EDLIN The Line Editor

SHIFT ←	Tab backwards
←	
→	Tab forwards
HOME	Move to start of file
END	Move to end of file
INS	Insert/overstrike mode
CTRL K	Erase to end of line
CTRL L	Refresh
CTRL R	Restore contents of current line
← or BS	Backspace
PG UP	Move up a screen
PG DN	Move down a screen
DEL	Delete a character

ENTER ↵ Insert line or Execute command

F1 DELETE ENTER
Remove all text between cursor and MARK line and place in restore buffer.

F1 FILE *pathname* ENTER
Stop editing this file and edit another file.

F1 GOTO *line* ENTER
Move window to this line number.

EDLIN The Line Editor

[*d:*][*path*] **EDLIN *filespec***

EDLIN Parameters

?	Display OK? prompt
#	Add text to end of file

<i>count</i>	Number of times
<i>line</i>	Line number
<i>line-a</i>	First line of range
<i>line-b</i>	Last line of range
<i>line-c</i>	Target line
<i>n</i>	Number of lines to write

Intra-Line Commands

F1 or -- **COPY1**
Copy one character from source line to edit line.

F2 *character* COPYTO
Copy up to *character* in source line to edit line.

F3 COPYLINE
Copy source line to edit line.

F4 *character* SKIPTO
Skip to specified *character* in source line.

F5 NEW TEMP
Copy edit line to source line to create a new source line.

DEL SKIP1
Skip one character in the source line.

-- **BACKSPACE**
Erase one character from command line.

ENTER ↵
Save text to left of cursor, or execute command.

CTRL Z
Leave insert mode.

ESC KILL
Clear the edit line.

INS INSERT
Enter and exit insert mode.

EDLIN The Line Editor - ERROR Messages

Inter-Line Commands

EDIT LINE

[*line* | .]

Edit *line* or current line.

APPEND LINES

[*n*] **A**

Add *n* lines from the input file on disk to the file in memory.

COPY LINES

[*line-a*] , [*line-b*] , *line-c* [, *count*] **C**

Copy a range of lines to *line-c* *count* times.

DELETE LINES

[*line-a*] [, *line-b*] **D**

Delete a range of lines or current line.

DISCARD AND QUIT

Q

Quit EDLIN and discard the edited file.

INSERT LINES

[*line* | . | #] **I**

Insert lines of text before *line*, current line, or at end of file.

LIST LINES

[*line-a*] [, *line-b*] **L**

Display a range of lines.

MOVE LINES

[*line-a*] , [*line-b*] , [*line-c*] **M**

Move a range of lines to *line-c*

PAGE

[*line-a*] [, *line-b*] **P**

Display a range and change current line.

SAVE AND EXIT

E

Exit EDLIN and save the edited file.

SEARCH

[*line-a*] [, *line-b*] [?] **S** *string*

Search range of lines for string.

SEARCH AND REPLACE

[*line-a*] [, *line-b*] [?] **R** *string-a*

[**CTRL Z** *string-b*]

Search range of lines and replace *string-a* with *string-b*.

TRANSFER LINES

[*line*] **T** [*filename*]

Transfer contents of *filename* before *line*.

WRITE LINES

[*n*] **W**

Write *n* lines from memory to disk file.

ERROR Messages

Errors may occur when reading from or writing to devices and disk drives. These errors cause the system to stop and output a message of this form:

type error action unit


Abort, Fail, Ignore, Retry?

When you receive a message like this, enter either:

- A** to Abort and end the program.
- F** to Fail the current MS-DOS system operation and to continue with the next system operation; for example in a batch file.
- I** to Ignore the error and try to continue, but you may lose data.
- R** to Retry the program again.

Warning

Do not change the diskette in the drive referred to, before pressing **A** or **I** or **R** or **F** as you will corrupt the new diskette.



Code 01500400 Y
Printed in Italy



olivetti