


QUICK REFERENCE

CLEUSEAU TEXT  
QUICK REFERENCE



Filing

F2.....Load from file  
 F3.....Save to file  
 CTRL\_V..Verify file with saved file

Mode setting

LABEL...Toggle label line on/off  
 CTRL\_J..Toggle Cleuseau TEXT on/off  
 CTRL\_O..Toggle INSERT/OVERWRITE

Moving

↑.....Move left one char  
 SHIFT←..Move to start of word (left)  
 CTRL\_A  
 CTRL\_←..Move to end of line (left)  
 CTRL\_Q  
 →.....Move right one char  
 SHIFT→..Move to start of word (right)  
 CTRL\_F  
 CTRL\_→..Move to end of line (right)  
 CTRL\_R  
 ↑.....Move up one line  
 SHIFT↑..Move to top of screen  
 CTRL\_↑..Move to top of file  
 CTRL\_W  
 ↓.....Move down one line  
 SHIFT↓..Move to bottom of screen  
 CTRL\_↓..Move to end of file  
 CTRL\_Z  
 CTRL\_G..Go to the next line

Character editing

BKSP.....Delete char left of cursor  
 CTRL\_H  
 DEL.....Delete char under cursor  
 ENTER...Insert CR and line feed  
 TAB.....Insert tab to column 1,9,17,...  
 CTRL\_I  
 CTRL\_P..Insert control char

Searching and replacing

F1.....Search forwards  
 F4.....Search backwards  
 CTRL\_N..Search for next\_string  
 CTRL\_S..Replace and search (PAUSE)  
 CTRL\_Y..Repeat replace and search

Selecting and pasting

F7.....Set select marker at cursor  
 F5.....Copy selection to paste buffer  
 F6.....Cut selection to paste buffer  
 CTRL\_E..Append to paste buffer  
 CTRL\_L..Lowercase selection  
 CTRL\_U..Uppercase selection  
 PASTE...Insert copy of paste buffer

Miscellaneous

BREAK...Cancel any command (CTRL\_C)  
 ESC.....n times, repeat command  
 F8.....MENU or BASIC (exit TEXT)  
 PRINT...Print screen on printer  
 SHIFT\_PRINT..Print file on printer  
 CTRL\_D..Display # of bytes/words/lines  
 CTRL\_X..HELP (CTRL\_X CTRL\_X for all)

## BASIC INSPECTOR QUICK REFERENCE

### Editing

**.RENUM** <range>[TO<num>][STEP<num>]...  
Renumber range of lines.  
**.MOVE** <range>[TO<num>][STEP<num>]...  
Move the range of lines.  
**.COPY** <range>[TO<num>][STEP<num>]...  
Copy range of lines.  
**.MIN** [<num>]...Minimize program size.  
**.DELCOM** <range>...Delete comments in range.  
**.SQUASH** <range>...Unnecessary blanks, end quotes and semi-colons removed.  
**.PACK** <range>[LEN<num>]...Pack program.  
**.EXPAND** <range>...Unpack program lines.  
**.KILL** <range>...Delete lines in range.  
(Doesn't update line #s.)

### Debugging

**.STOP** <range>[=<string>]...Insert stop points. Shown as |.  
**.PRINT** <range>[=<string>]...Insert print points. Shown as ..  
**.CONT** <range>[=<string>]...Insert continue points. Shown as - -  
**.OFF** <range>[=<string>]...Delete stop, print or continue points.  
**.LOG**:.....Print pt log to screen.  
**.LOG** [<num>].....Print pt log file num.  
**.LOG**.....Print pt log to printer.

### Miscellaneous

**CTRL\_U**.....Delete input line.  
**CTRL\_X**.....HELP. BASIC Inspector.  
**ESC**.....Next line number.  
**.FILES**.....Files & sizes (screen).  
**.LFILES**.....Files & sizes (printer).  
**.LIST**<range>[=<string>]...Lines in range with <string> (screen).  
**.LLIST**<range>[=<string>]...Lines in range with <string> (printer).  
**.STEP** <num>.....Set auto line num step.  
**.(dot)**.....List next line to execute and the GOSUB/RETURN stack.

To install Cleuseau's software after a cold restart:

**CALL 63012**

Cleuseau will appear in the lower right corner of the menu.

To disable Cleuseau, as if it were cold restarted or removed:

**CALL 911**

### TEXT examples

To move to the 100th line in the file:

**CTRL\_↑ ESC 99 ENTER CTRL\_G**

To count the number of bytes, words, or lines the file:

**CTRL\_↓ CTRL\_D**

To count the number of times a word occurs in the file:

**CTRL\_↑ ESC R ENTER F1 <word>ENTER**

To replace & search, checking each time:

**CTRL\_S <string>ENTER <string>ENTER**

first <string> = search string  
second <string> = replace string

At each occurrence press:

**CTRL\_N** to search (skip)  
**CTRL\_Y** to replace and search

Use **F1** and **F4** to control the search direction.

To reduce a program to its minimum size:

**.MIN** [<num>]  
Sure? Y

where <num> is the maximum line length desired.

To list all lines that assign X a value:

**.LIST -X-**

To list all lines that GOSUB 1000:

**.LIST -GOSUB 1000**

To trace program execution on the printer:

**.LLOG**  
**.PRINT**  
**RUN**